

Instructions to remove UKT data from server installations of MAPS (v1.0)

## Removing National Grid UKT data from server installations of MAPS Viewer

### Background

The last release of the National Grid UKT CD was April 2008. The CD has now been withdrawn and the National Grid Transmission is now available via the Linesearch website:

<http://www.linesearch.org/>

If you are a utility, council or similar organisation you may wish to request a copy of the National Grid CD to load into your own GIS. This CD contains shape files of their national networks (gas and electricity). Contact address:

National Grid Transmission  
Land and Development  
Asset Protection  
PO Box 3483  
Warwick  
CV34 6TG

### Please note:

- Running the MAPS Viewer software in a client-server configuration is not officially supported - the intended use of the MAPS Viewer is to run from a local hard disk, with data optionally installed or read from disc.
- It is assumed that an administrative user with knowledge of Windows administration will carry out these instructions.
- If you have never received and installed the National Grid UKT CD then you don't need to follow these instructions.
- The National Grid MAPS DVD July 2008 and onwards contains the National Grid distribution network. In the EA, EM, NL, NW, and WM areas the UKT data will continue to be available. Outside these network areas the tiles that contain the National Grid Transmission will not be present and will not be listed as being held.
- To obtain National Grid UKT information you should use the Linesearch web site or request a CD of GIS data as detailed above.


## Instructions to remove UKT data from server installations of MAPS (v1.0)

### Instructions

If you have a server installation and do not have any National Grid data installed then no changes are required to your installation.

If you have a server installation and National Grid data installed then please follow one of the four remaining sections of this document.

### Flow chart to assist with following relevant section



Instructions to remove UKT data from server installations of MAPS (v1.0)

## 1. National Grid only installed

1.1 If you have previously installed the National Grid UKT CD **and** the National Grid MAPS DVD:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder (because this will remove old distribution and any previously installed UKT files)
3. Copy the contents of the \data\gas\NG folder from the National Grid MAPS DVD \National Grid data folder to your server National Grid folder.

1.2 If you have previously installed the National Grid UKT CD **but NOT** the National Grid MAPS DVD then the National grid installation should be removed. As only UKT data was previously being viewed and this is no longer being supplied by National Grid then a full removal of MAPS is recommended:

1. Create an unregister.bat in your server MAPS\EXE folder with contents:  
regsvr32 /u Core\NMContainer.ocx  
regsvr32 /u Core\NMEngine.ocx  
regsvr32 /u Server\ConfigurationS.dll  
regsvr32 /u Server\DataQuery.dll  
regsvr32 /u Server\FeatureQuery.dll  
regsvr32 /u Server\SearchGazetteer.dll  
regsvr32 /u Server\VersionQuery.dll
2. Run the script on each client
3. Delete any start menu items and desktop shortcuts to MAPS on the client
4. Once all client machines have had the software removed you can locate and delete the MAPS installation folder on the server.
5. If the MAPS software was on the local hard disk of the client then you will need an unregister.bat on each client. On each client this should be run this and the MAPS folder deleted.

Instructions to remove UKT data from server installations of MAPS (v1.0)

## 2. WWU and National Grid installed

2.1 If you have previously installed the National Grid UKT CD **and** the National Grid MAPS DVD:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder (because this will remove old distribution and any previously installed UKT files)
3. Copy the contents of the \data\gas\NG folder from the National Grid MAPS DVD \National Grid data folder to your server National Grid folder.

2.2 If you have previously installed the National Grid UKT CD **but NOT** the National Grid MAPS DVD then the National grid data owner and data needs to be removed:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder
3. Locate your server maps exe folder e.g. c:\maps\exe
4. Edit the MAPS.INI file.
5. Change the [OWNERS] section to read:  
OwnerCount=1  
Owner1=WWU
6. Locate the maps exe core folder
7. Delete file NG\_CD\_MAPS.chm
8. Delete folder 2
9. Delete folder {8A41DDF3-177B-44e4-A821-4A409C3E1611}
10. Change to the subfolder {510D3D51-07D2-4677-87AA-09A1BD0B6279}
11. Edit Bootstrap.ini file.
12. Change the "UserType=200020" line to:  
UserType=200000
13. Locate your server maps config folder e.g. c:\maps\config
14. Delete file NG\_CD\_MAPS\_CONFIG.NMC
15. Delete file NG\_CD\_MAPS\_Server\_Config.nmc

Instructions to remove UKT data from server installations of MAPS (v1.0)

### 3. SGN and National Grid installed

3.1 If you have previously installed the National Grid UKT CD **and** the National Grid MAPS DVD:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder (because this will remove old distribution and any previously installed UKT files)
3. Copy the contents of the \data\gas\NG folder from the National Grid MAPS DVD \National Grid data folder to your server National Grid folder.

3.2 If you have previously installed the National Grid UKT CD **but NOT** the National Grid MAPS DVD then the National grid data owner and data needs to be removed:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder
3. Locate your server maps exe folder e.g. c:\maps\exe
4. Edit the MAPS.INI file.
5. Change the [OWNERS] section to read:  
OwnerCount=1  
Owner1=SGN
6. Locate the maps exe core folder
7. Delete file NG\_CD\_MAPS.chm
8. Delete folder 2
9. Delete folder {8A41DDF3-177B-44e4-A821-4A409C3E1611}
10. Change to the subfolder {F2F7CA72-661A-4293-931D-3CE904DC1FF6}
11. Edit Bootstrap.ini file.
12. Change the "UserType=100040" line to:  
UserType=100000
13. Locate your server maps config folder e.g. c:\maps\config
14. Delete file NG\_CD\_MAPS\_CONFIG.NMC
15. Delete file NG\_CD\_MAPS\_Server\_Config.nmc

Instructions to remove UKT data from server installations of MAPS (v1.0)

#### 4. WWU, SGN and National Grid installed

4.1 If you have previously installed the National Grid UKT CD **and** the National Grid MAPS DVD:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder (because this will remove old distribution and any previously installed UKT files)
3. Copy the contents of the \data\gas\NG folder from the National Grid MAPS DVD \National Grid data folder to your server National Grid folder.

4.2 If you have previously installed the National Grid UKT CD **but NOT** the National Grid MAPS DVD then the National grid data owner and data needs to be removed:

1. Locate your server maps data folder e.g. c:\maps\data\gas\
2. Delete the NG folder
3. Locate your server maps exe folder e.g. c:\maps\exe
4. Edit the MAPS.INI file.
5. Change the [OWNERS] section to read:  
    OwnerCount=2  
    Owner1=SGN  
    Owner2=WWU
6. Locate the maps exe core folder
7. Delete file NG\_CD\_MAPS.chm
8. Delete folder 2
9. Delete folder {8A41DDF3-177B-44e4-A821-4A409C3E1611}
10. Change to the subfolder {510D3D51-07D2-4677-87AA-09A1BD0B6279}
11. Edit Bootstrap.ini file.
12. Change the "UserType=200060" line to:  
    UserType=200040
13. Change to the subfolder {F2F7CA72-661A-4293-931D-3CE904DC1FF6}
14. Edit Bootstrap.ini file.
15. Change the "UserType=1000C0" line to:  
    UserType=100080
16. Locate your server maps config folder e.g. c:\maps\config
17. Delete file NG\_CD\_MAPS\_CONFIG.NMC
18. Delete file NG\_CD\_MAPS\_Server\_Config.nmc